



## Pangolin Analog Waveform Generator User Manual and Documentation

July 2, 2025

# Contents

<b>1</b>	<b>Introduction</b>	<b>2</b>
1.1	Purpose . . . . .	2
1.2	Key Features . . . . .	2
<b>2</b>	<b>System Requirements</b>	<b>2</b>
2.1	Hardware Requirements . . . . .	2
2.2	Software Requirements . . . . .	3
<b>3</b>	<b>Installation Guide</b>	<b>3</b>
3.1	Python Installation . . . . .	3
3.2	Library Installation . . . . .	3
3.3	Running the Application . . . . .	3
<b>4</b>	<b>User Interface Overview</b>	<b>4</b>
4.1	Main Window Components . . . . .	4
<b>5</b>	<b>Getting Started</b>	<b>6</b>
5.1	Generating a Basic Waveform . . . . .	6
5.2	Outputting to DAQ . . . . .	6
<b>6</b>	<b>Troubleshooting</b>	<b>6</b>
6.1	Electrical Specifications . . . . .	6
6.2	Software Architecture . . . . .	6
<b>7</b>	<b>Appendices</b>	<b>6</b>
7.1	Sample Text File Format . . . . .	6
7.2	Version History . . . . .	6

# 1 Introduction

## 1.1 Purpose

The Pangolin Waveform Generator is a Python SDK application (Figure 1.) designed to utilize analog command inputs available on the Match DSP. The application interfaces with a Data Acquisition System (DAQ), such as National Instruments hardware, to generate and output a variety of waveform signals (Figure 2.). It supports standard waveforms (sine, square, triangle, sawtooth), specialized cycloid waveforms, and can accommodate custom waveform shapes based on user requirements.

## 1.2 Key Features

- Dual-axis (X and Y) waveform generation
- Support for standard, cycloids, and custom waveforms
- Real-time waveform visualization
- National Instruments DAQ hardware integration




Figure 1: Main application window

## 2 System Requirements

### 2.1 Hardware Requirements

- National Instruments DAQ device (compatible with NI-DAQmx)
- List of NI DAQ tested at the moment the release of these manual:
  - NI USB-6003, NI USB-6211




Figure 2: Match-dsp and DAQ connections

## 2.2 Software Requirements

- Python 3.7 or later
- Required Python packages:
  - PyQt5
  - NumPy
  - SciPy
  - Matplotlib
  - NI-DAQmx

## 3 Installation Guide

### 3.1 Python Installation

1. Download Python from <https://www.python.org/downloads/>
2. Run the installer, checking "Add Python to PATH" (Figure 3.)
3. Verify installation by running `python --version` in Command Prompt

### 3.2 Library Installation

Run these commands in Command Prompt:

```
pip install pyqt5 numpy scipy matplotlib nidaqmx
```

### 3.3 Running the Application

1. Navigate to the application directory
2. Run the main script:

```
python pangolin_waveform_generator.py
```



Figure 3: Python installation screen




Figure 4: Successful library installation

## 4 User Interface Overview

### 4.1 Main Window Components

- **Waveform Selection Panel**

- Standard waveform dropdown (sine, square, triangle, sawtooth, text input)
- Cycloid waveform dropdown (triangle, sawtooth)
- Parameter controls (amplitude, frequency, number of points, etc)
- The Text Input Waveform allows the user to input a precomputed custom waveform. It is recommended to upload a text file that includes one period (or full cycle) of the desired waveform.

- **Axis Control Panel**

- X/Y axis selection with color coding (x- axis parameter will be saved in light blue and y- axis parameters will be saved in light red). If no parameters are saved on a particular axis, parameters color background will be white.
- Send to axis buttons will save the current waveform parameters in a selected galvanometer axis x or y.

```

Command Prompt
Microsoft Windows [Version 10.0.22631.5039]
(c) Microsoft Corporation. All rights reserved.

C:\Users\erik>cd Desktop
C:\Users\erik\Desktop>cd "Match DSP API"
C:\Users\erik\Desktop\Match DSP API>cd Python
C:\Users\erik\Desktop\Match DSP API\Python>cd "Analog control"
C:\Users\erik\Desktop\Match DSP API\Python\Analog control>python pangolin_waveform_generator.py/

```

Figure 5: Running the main script

- Mirror mode checkbox allows to y-axis to mimic the behavior of x-axis
- **Graph Display**
  - Real-time waveform visualization
  - Update/Clear graph buttons
- **DAQ Control**
  - Start/Stop DAQ buttons control when the DAQ should start producing the output voltage or to stop
  - Data selection will provide support only for National instrument devices at the moment of the release
  - Sample rate depends of your DAQ capabilities




Figure 6: Main Window Components

## 5 Getting Started

### 5.1 Generating a Basic Waveform

1. Select "X-Axis" from the axis dropdown
2. Choose "Sine" from the standard waveform dropdown
3. Set amplitude to 5V and frequency to 1Hz
4. Click "Send to Axis"
5. View the waveform in the graph display

### 5.2 Outputting to DAQ

1. Configure a waveform as above
2. Click "Send to DAQ" to start output
3. Click "Stop DAQ" to end output

## 6 Troubleshooting

Issue	Solution
DAQ not detected	Verify NI-DAQmx library is installed and device is connected
No waveform displayed	Check axis selection and click "Update Graph"
Text file not loading	Ensure file contains numeric values only
DAQ output stops unexpectedly	Check for voltage limits ( $\pm 10V$ )

Table 1: Troubleshooting guide

### 6.1 Electrical Specifications

- Output Voltage Range:  $\pm 10V$
- Maximum Sampling Rate: [Your DAQ's maximum rate]

### 6.2 Software Architecture

- **GUI Framework:** PyQt5
- **Plotting:** Matplotlib
- **Signal Processing:** NumPy, SciPy
- **Hardware Interface:** NI-DAQmx

## 7 Appendices

### 7.1 Sample Text File Format

1.0  
2.0  
3.0  
2.0  
1.0

### 7.2 Version History

- 1.0: Initial release